

This document provides additional assistance with wiring your Extron IP Link Pro Control Processor to your device. Different components may require a different wiring scheme than those listed below.

For complete operating instructions, refer to the user's manual for the specific IP Link Pro Control Processor or the documentation supplied by the manufacturer of the controlled device.

For more information on using Global Scriptor Modules, refer to the "[Guide to Using Scriptor Modules](#)" document.

## Device Specifications

Device Type: Video Projector  
Manufacturer: NEC  
Firmware Version: N/A  
Model(s): NP-PA803UL, NP-PA653UL

## Tested on the Following Software and Firmware Versions

IP Link Pro Control Processor Firmware	Global Scriptor Version
3.06.0001-b002	2.3.1

## Version History

Module Version	Date	Notes
1_1_1_0	4/30/2020	Added Lens Control command. Updated required polling rate from 10s to 60s based on customer feedback. Device Status <ul style="list-style-type: none"><li>Removed Pump Error</li><li>Added Ballast Communication Error, Iris Calibration Error, Lens Not Properly Installed, and Multiple Errors</li></ul> Input Renamed PC → Computer
1_0_1_0	11/13/2018	Initial Version

---

## Module Notes

- Unidirectional variable must be set to 'True' if status is not required. Default value is 'False'.  
Example: `InterfaceName.Unidirectional = 'True'`
- connectionCounter variable must be set to the number of queries that will be sent to the device before displaying 'Disconnected' if no response is received. Default value is 15.  
Example: `InterfaceName.connectionCounter = 5`
- To prevent the device from potentially locking up, send Update commands at least 10 seconds apart, as per manufacturer's requirements.

## Supported Classes and Examples

<b>SerialClass</b>
<code>InterfaceName = ModuleName.SerialClass(ProcessorName, 'COM1', Model='NP-PA803UL')</code>
<b>SerialOverEthernetClass</b>
<code>InterfaceName = ModuleName.SerialOverEthernetClass('192.168.254.254', 2001, Model='NP-PA803UL')</code>
<b>EthernetClass</b>
<code>InterfaceName = ModuleName.EthernetClass('192.168.254.254', 7142, Model='NP-PA803UL')</code>

---

## Update Loop Sample Code

This sample code accounts for the 10 second wait needed between Update commands as manufacturer specified.

One Update command will go out every ten seconds, cycling through the list of commands specified. To stop the loop at any time use .Cancel() and .Restart() to continued.

```
from extronlib.system import Clock, MESet, Timer, Wait
from itertools import cycle
```

```
UpdateList = ['Power', 'Input', 'Volume', 'VideoMute']
cycleUpdateList = cycle(UpdateList)
```

```
def cycleUpdateFunc():
    cmdName = next(cycleUpdateList)
    InterfaceName.Update(cmdName)
    TenSecTimer.Restart()
```

```
TenSecTimer = Wait(10, cycleUpdateFunc)
TenSecTimer.Cancel()
```

```
def Initialize():
    TenSecTimer.Restart()
```

```
Example to Stop the loop:    TenSecTimer.Cancel()
Example to Restart the loop: TenSecTimer.Restart()
```

## Control Commands

Format with Qualifier:

```
InterfaceName.Set(Command, Value, {'Qualifier Key': 'Qualifier Value'})
```

Format without Qualifier:

```
InterfaceName.Set(Command, Value)
```

<b>Command</b> <b>AspectRatio</b>	Value '4:3' 'Full' '16:10' <sup>1</sup> 'Auto'	Value 'Letterbox' <sup>2</sup> 'Zoom' <sup>2</sup> '15:9' <sup>1</sup> 'Normal'	Value '16:9' <sup>3</sup> '5:4' <sup>1</sup> 'Native' <sup>1</sup>
# AspectRatio example InterfaceName.Set('AspectRatio', '4:3')			
<b>Command</b> <b>AudioMute</b>	Value 'On'	Value 'Off'	
# AudioMute example InterfaceName.Set('AudioMute', 'On')			
<b>Command</b> <b>AutoImage</b>	Value None		
# AutoImage example InterfaceName.Set('AutoImage', None)			
<b>Command</b> <b>Freeze</b>	Value 'On'	Value 'Off'	
# Freeze example InterfaceName.Set('Freeze', 'On')			
<b>Command</b> <b>Input</b>	Value 'HDMI 1' 'Computer'	Value 'HDMI 2' 'HDBaseT'	Value 'DisplayPort'
# Input example InterfaceName.Set('Input', 'HDMI 1')			
<b>Command</b> <b>LampMode</b>	Value 'Normal' 'Long Life'	Value 'Eco 1'	Value 'Eco 2'
# LampMode example InterfaceName.Set('LampMode', 'Normal')			
<b>Command</b> <b>LensControl</b>	Value 'Plus'	Value 'Minus'	Value 'Stop'
<b>Qualifier Key</b> 'Type'	Qualifier Value 'Zoom' 'Lens Shift (V)'	Qualifier Value 'Focus'	Qualifier Value 'Lens Shift (H)'
# LensControl example InterfaceName.Set('LensControl', 'Plus', {'Type': 'Zoom'})			
<b>Command</b> <b>LensProfile</b>	Value '1' – '2'		
# LensProfile example InterfaceName.Set('LensProfile', '1')			
<b>Command</b> <b>LensProfileControl</b> <sup>4</sup>	Value 'Move'	Value 'Store'	Value 'Reset'
# LensProfileControl example InterfaceName.Set('LensProfileControl', 'Move')			
<b>Command</b>	Value	Value	Value

## Global Scriptor Module Communication Sheet

<b>MenuNavigation</b>	'Up' 'Right' 'Menu'	'Down' 'Enter'	'Left' 'Exit'
# MenuNavigation example InterfaceName.Set('MenuNavigation', 'Up')			
<b>Command</b> <b>OnScreenDisplay</b>	Value 'On'	Value 'Off'	
# OnScreenDisplay example InterfaceName.Set('OnScreenDisplay', 'On')			
<b>Command</b> <b>Power</b>	Value 'On'	Value 'Off'	
# Power example InterfaceName.Set('Power', 'On')			
<b>Command</b> <b>Shutter</b> <sup>5</sup>	Value 'Open'	Value 'Close'	
# Shutter example InterfaceName.Set('Shutter', 'Open')			
<b>Command</b> <b>VideoMute</b>	Value 'On'	Value 'Off'	
# VideoMute example InterfaceName.Set('VideoMute', 'On')			
<b>Command</b> <b>Volume</b>	Value 0 to 31 in steps of 1		
# Volume example InterfaceName.Set('Volume', 31)			

<sup>1</sup> Not supported for HDTV/SDTV signals

<sup>2</sup> Not supported for Computer signals

<sup>3</sup> Corresponds to Wide Screen for HDTV/SDTV signals

<sup>4</sup> Lens Profile must be set before sending this command.

<sup>5</sup> Only available on NP-PA803UL.

## Status Available

For all commands, call Update to receive the latest status. ConnectionStatus does not support the Update function. ConnectionStatus is triggered by the device providing a successful response to other Update function calls.

### Format with Qualifier:

```
InterfaceName.Update(Command, {'Qualifier Key': 'Qualifier Value'})
Value = InterfaceName.ReadStatus(Command, {'Qualifier Key': 'Qualifier Value'})
InterfaceName.SubscribeStatus(Command, {'Qualifier Key': 'Qualifier Value'},
```

FeedbackHandler)

FeedbackHandler will be called only when the specified qualifier gets a new status.

### Format without Qualifier:

```
InterfaceName.Update(Command)
Value = InterfaceName.ReadStatus(Command)
InterfaceName.SubscribeStatus(Command, None, FeedbackHandler)
FeedbackHandler will be called when any qualifier gets a new status.
```

Command	Value	Value	Value
<b>AudioMute</b> <sup>1</sup>	'On'	'Off'	
# AudioMute example InterfaceName.Update('AudioMute') Value = InterfaceName.ReadStatus('AudioMute') InterfaceName.SubscribeStatus('AudioMute', None, FeedbackHandler)			
Command	Value	Value	Value
<b>ConnectionStatus</b>	'Connected'	'Disconnected'	
# ConnectionStatus example Value = InterfaceName.ReadStatus('ConnectionStatus') InterfaceName.SubscribeStatus('ConnectionStatus', None, FeedbackHandler)			
Command	Value	Value	Value
<b>DeviceStatus</b>	'Normal'	'Lamp Cover Error'	'Temperature Error'
	'Fan Failure'	'Power Error'	'Lamp Error'
	'Lamp Life Expired'	'Lamp Beyond Limit'	'Format Error'
	'FPGA Error'	'Temp Sensor Failure'	'Lamp Housing Error'
	'Lamp Data Error'	'Mirror Cover Error'	'High Temperature'
	'Sensor Error'	'Ballast Communication Error'	'Iris Calibration Error'
	'Lens Not Properly Installed'	'Multiple Errors'	
# DeviceStatus example InterfaceName.Update('DeviceStatus') Value = InterfaceName.ReadStatus('DeviceStatus') InterfaceName.SubscribeStatus('DeviceStatus', None, FeedbackHandler)			
Command	Value		
<b>FilterUsage</b>	Hours		
# FilterUsage example InterfaceName.Update('FilterUsage') Value = InterfaceName.ReadStatus('FilterUsage') InterfaceName.SubscribeStatus('FilterUsage', None, FeedbackHandler)			
Command	Value	Value	
<b>Freeze</b> <sup>1</sup>	'On'	'Off'	
# Freeze example InterfaceName.Update('Freeze') Value = InterfaceName.ReadStatus('Freeze') InterfaceName.SubscribeStatus('Freeze', None, FeedbackHandler)			

Global Scripter Module  
Communication Sheet

Command Input <sup>1</sup>	Value 'HDMI 1' 'Computer'	Value 'HDMI 2' 'HDBaseT'	Value 'DisplayPort'
# Input example InterfaceName.Update('Input') Value = InterfaceName.ReadStatus('Input') InterfaceName.SubscribeStatus('Input', None, FeedbackHandler)			
Command LampMode	Value 'Normal' 'Long Life'	Value 'Eco 1'	Value 'Eco 2'
# LampMode example InterfaceName.Update('LampMode') Value = InterfaceName.ReadStatus('LampMode') InterfaceName.SubscribeStatus('LampMode', None, FeedbackHandler)			
Command LampUsage	Value Hours		
# LampUsage example InterfaceName.Update('LampUsage') Value = InterfaceName.ReadStatus('LampUsage') InterfaceName.SubscribeStatus('LampUsage', None, FeedbackHandler)			
Command LensProfile	Value '1' – '2'		
# LensProfile example InterfaceName.Update('LensProfile') Value = InterfaceName.ReadStatus('LensProfile') InterfaceName.SubscribeStatus('LensProfile', None, FeedbackHandler)			
Command OnScreenDisplay <sup>1</sup>	Value 'On'	Value 'Off'	
# OnScreenDisplay example InterfaceName.Update('OnScreenDisplay') Value = InterfaceName.ReadStatus('OnScreenDisplay') InterfaceName.SubscribeStatus('OnScreenDisplay', None, FeedbackHandler)			
Command Power <sup>1</sup>	Value 'On' 'Cooling Down'	Value 'Off'	Value 'Warming Up'
# Power example InterfaceName.Update('Power') Value = InterfaceName.ReadStatus('Power') InterfaceName.SubscribeStatus('Power', None, FeedbackHandler)			
Command VideoMute <sup>1</sup>	Value 'On'	Value 'Off'	
# VideoMute example InterfaceName.Update('VideoMute') Value = InterfaceName.ReadStatus('VideoMute') InterfaceName.SubscribeStatus('VideoMute', None, FeedbackHandler)			
Command Volume	Value 0 to 31 in steps of 1		
# Volume example InterfaceName.Update('Volume') Value = InterfaceName.ReadStatus('Volume') InterfaceName.SubscribeStatus('Volume', None, FeedbackHandler)			

<sup>1</sup> These commands share the same Update command string. One Update will return status for all of them.

---

---

## Cable and Adapter Requirements

Captive Screw to Female DB9 RS-232 Serial Cable

## Notes for the Device

---

---

## Serial communication

**Port Type:** RS-232

**Baud Rate:** 38400


**Data Bits:** 8

**Parity:** None


**Stop Bits:** One

**Flow Control:** None

## Pin Assignments Diagram



Signal	Main Cable	Pin	Signal
TxD	→	2	RxD
RxD	←	3	TxD
GND	→	5	GND





---

---

## Network communication

When configuring the Ethernet module, be sure device settings match those of the Global Scriptor ethernet interface.

<b>Port Type:</b>	Ethernet
<b>Default Port:</b>	7142
<b>Logon Credentials Supported:</b>	No
<b>Multi-Connection Capabilities:</b>	Undetermined
<b>Port Changeability:</b>	No

---

---

## Ethernet Module Configuration Description

Please refer to user manual for settings and changes to the network communication

## Notes for the Device

## Appendix A. Set Commands

Aspect Ratio 15:9	\x03\x10\x00\x00\x05\x18\x00\x00\x0D\x00=
Aspect Ratio 16:10	\x03\x10\x00\x00\x05\x18\x00\x00\x0C\x00<
Aspect Ratio 16:9	\x03\x10\x00\x00\x05\x18\x00\x00\x02\x002
Aspect Ratio 4:3	\x03\x10\x00\x00\x05\x18\x00\x00\x00\x000
Aspect Ratio 5:4	\x03\x10\x00\x00\x05\x18\x00\x00\x0B\x00;
Aspect Ratio Auto	\x03\x10\x00\x00\x05\x18\x00\x00\x0F\x00?
Aspect Ratio Full	\x03\x10\x00\x00\x05\x18\x00\x00\x06\x006
Aspect Ratio Letterbox	\x03\x10\x00\x00\x05\x18\x00\x00\x01\x001
Aspect Ratio Native	\x03\x10\x00\x00\x05\x18\x00\x00\x0E\x00>
Aspect Ratio Normal	\x03\x10\x00\x00\x05\x18\x00\x00\x10\x00@
Aspect Ratio Zoom	\x03\x10\x00\x00\x05\x18\x00\x00\x07\x007
Audio Mute Off	\x02\x13\x00\x00\x00\x15
Audio Mute On	\x02\x12\x00\x00\x00\x14
Auto Image None	\x02\x0F\x00\x00\x02\x05\x00\x18
Freeze Off	\x01\x98\x00\x00\x01\x02\x9C
Freeze On	\x01\x98\x00\x00\x01\x01\x9B
Input Computer	\x02\x03\x00\x00\x02\x01\x01\x09
Input DisplayPort	\x02\x03\x00\x00\x02\x01\xA6\xAE
Input HDBaseT	\x02\x03\x00\x00\x02\x01\xBF\xC7
Input HDMI 1	\x02\x03\x00\x00\x02\x01\xA1\xA9
Input HDMI 2	\x02\x03\x00\x00\x02\x01\xA2\xAA
Lamp Mode Eco 1	\x03\xB1\x00\x00\x02\x07\x02\xBF
Lamp Mode Eco 2	\x03\xB1\x00\x00\x02\x07\x03\xC0
Lamp Mode Long Life	\x03\xB1\x00\x00\x02\x07\x04\xC1
Lamp Mode Normal	\x03\xB1\x00\x00\x02\x07\x00\xBD
Lens Control Minus Type Focus	\x02\x18\x00\x00\x02\x01\x81\x9E
Lens Control Minus Type Lens Shift (H)	\x02\x18\x00\x00\x02\x02\x81\x9F
Lens Control Minus Type Lens Shift (V)	\x02\x18\x00\x00\x02\x03\x81\xA0
Lens Control Minus Type Zoom	\x02\x18\x00\x00\x02\x00\x81\x9D
Lens Control Plus Type Focus	\x02\x18\x00\x00\x02\x01\x7F\x9C
Lens Control Plus Type Lens Shift (H)	\x02\x18\x00\x00\x02\x02\x7F\x9D
Lens Control Plus Type Lens Shift (V)	\x02\x18\x00\x00\x02\x03\x7F\x9E
Lens Control Plus Type Zoom	\x02\x18\x00\x00\x02\x00\x7F\x9B
Lens Control Stop Type Focus	\x02\x18\x00\x00\x02\x01\x00\x1D
Lens Control Stop Type Lens Shift (H)	\x02\x18\x00\x00\x02\x02\x00\x1E
Lens Control Stop Type Lens Shift (V)	\x02\x18\x00\x00\x02\x03\x00\x1F
Lens Control Stop Type Zoom	\x02\x18\x00\x00\x02\x00\x00\x1C
Lens Profile 1	\x02'\x00\x00\x01\x00*
Lens Profile 2	\x02'\x00\x00\x01\x01+
Lens Profile Control Move	\x02\x1F\x00\x00\x01\x00"
Lens Profile Control Reset	\x02\x1F\x00\x00\x01\x02\$
Lens Profile Control Store	\x02\x1F\x00\x00\x01\x01#

## Global Scriptor Module Communication Sheet

Revision: 4/30/2020

<b>Menu Navigation Down</b>	\x02\x0F\x00\x00\x02\x08\x00\x1B
<b>Menu Navigation Enter</b>	\x02\x0F\x00\x00\x02\x0B\x00\x1E
<b>Menu Navigation Exit</b>	\x02\x0F\x00\x00\x02\x0C\x00\x1F
<b>Menu Navigation Left</b>	\x02\x0F\x00\x00\x02\x0A\x00\x1D
<b>Menu Navigation Menu</b>	\x02\x0F\x00\x00\x02\x06\x00\x19
<b>Menu Navigation Right</b>	\x02\x0F\x00\x00\x02\x09\x00\x1C
<b>Menu Navigation Up</b>	\x02\x0F\x00\x00\x02\x07\x00\x1A
<b>On Screen Display Off</b>	\x02\x14\x00\x00\x00\x16
<b>On Screen Display On</b>	\x02\x15\x00\x00\x00\x17
<b>Power Off</b>	\x02\x01\x00\x00\x00\x03
<b>Power On</b>	\x02\x00\x00\x00\x00\x02
<b>Shutter Close</b>	\x02\x16\x00\x00\x00\x18
<b>Shutter Open</b>	\x02\x17\x00\x00\x00\x19
<b>Video Mute Off</b>	\x02\x11\x00\x00\x00\x13
<b>Video Mute On</b>	\x02\x10\x00\x00\x00\x12
<b>Volume 0</b>	\x03\x10\x00\x00\x05\x05\x00\x00\x00\x1D
<b>Volume 31</b>	\x03\x10\x00\x00\x05\x05\x00\x00\x1F\x00<

### Appendix B. Update Commands

<b>Power</b>	\x00\xBF\x00\x00\x01\x02\xC2
--------------	------------------------------

