Revision: 8/29/2018

This document provides additional assistance with wiring your Extron IP Link Pro Control Processor to your device. Different components may require a different wiring scheme than those listed below.

For complete operating instructions, refer to the user's manual for the specific IP Link Pro Control Processor or the documentation supplied by the manufacturer of the controlled device.

For more information on using Global Scripter Modules, refer to the "Guide to Using Scripter Modules" document.

Device Specifications

Device Type: Display Manufacturer: Sharp Firmware Version: N/A

Model(s): LC-90LE657U, LC-60C6500U, LC-60C7500U, LC-60LE650U, LC-60LE655U, LC-60LE657U,

LC-60LE755U, LC-60LE757U, LC-60LE857U, LC-70C6500U, LC-70C7500U, LC-70LE650U, LC-70LE655U, LC-70LE657U, LC-70LE755U, LC-70LE757U, LC-70LE857U, LC-80C6500U,

LC-80LE650U, LC-80LE657U, LC-80LE757U, LC-80LE857U, LC-90LE650U

Tested on the Following Software and Firmware Versions

IP Link Pro Control Processor Firmware	Global Scripter Version
2.06.0002-b002	1.4.2

Version History

Module Version	Date	Notes
1_0_7_0	8/29/2018	Initial Version

Revision: 8/29/2018

Module Notes

- Unidirectional variable must be set to 'True' if status is not required. Default value is 'False'.
 Example: InterfaceName.Unidirectional = 'True'
- connectionCounter variable must be set to the number of queries that will be sent to the device before displaying 'Disconnected' if no response is received. Default value is 15.

Example: InterfaceName.connectionCounter = 5

If login credentials are required, devicePassword and deviceUsername must be set accordingly.

Example: InterfaceName.devicePassword = 'extron'

Supported Classes and Examples

SerialClass

InterfaceName = ModuleName.SerialClass(ProcessorName, 'COM1', Model='LC-90LE657U')

SerialOverEthernetClass

InterfaceName = ModuleName.SerialOverEthernetClass('192.168.254.254', 2001, Model='LC-90LE657U')

EthernetClass

InterfaceName = ModuleName.EthernetClass('192.168.254.254', 10002, Model='LC-90LE657U')

Revision: 8/29/2018

Control Commands

Format with Qualifier:

InterfaceName.Set(Command, Value, {'Qualifier Key': 'Qualifier Value'})

Format without Qualifier:

InterfaceName.Set(Command, Value)

Command	Value	Value	Value
AspectRatio	'Side Bar'	'S.Stretch'	'Zoom [AV]'
•	'Stretch [AV]'	'Normal [PC]'	'Zoom [PC]'
	'Stretch [PC]'	'Dot by Dot [PC]'	'Full Screen [AV]'
		,	ruii screen [AV]
	'Auto'	'Original'	
# AspectRatio example InterfaceName.Set('As	e spectRatio', 'Side Bar')		
Command	Value		
AudioInput	None		
<pre># AudioInput example InterfaceName.Set('Augustian</pre>	udioInput', None)		
Command	Value	Value	
AudioMute	'On'	'Off'	
# AudioMute example InterfaceName.Set('Au	udioMute', 'On')		
Command	Value		
ChannelDTVAir	'Channel'		
# ChannelDTVAirDiscre InterfaceName.Set('Ch	- ete example nannelDTVAirDiscrete', 'Ch	annel')	
Command	Value		
ChannelDTVCableMajor	'Channel'		
# ChannelDTVCableMajorDiscrete example InterfaceName.Set('ChannelDTVCableMajorDiscrete', 'Channel')			
Command	Value		
ChannelDTVCableMinor	'Channel'		
# ChannelDTVCableMinorDiscrete example InterfaceName.Set('ChannelDTVCableMinorDiscrete', 'Channel')			
Command	Value		
ChannelDTVCable2	'Channel'		
	# ChannelDTVCable2Discrete example InterfaceName.Set('ChannelDTVCable2Discrete', 'Channel')		
Command	Value		
ChannelDTVCable3	'Channel'		
# ChannelDTVCable3Discrete example			

Revision: 8/29/2018

InterfaceName.Set	('ChannelDTVCable3Discr	ete', 'Channel')		
Command	Value	Value		
ChannelStep	'Up'	'Down'		
# ChannelStep exa InterfaceName.Set	mple ('ChannelStep', 'Up')	·		
Command	Value			
ChannelTV	'Channel'			
# ChannelTVDiscre InterfaceName.Set	te example ('ChannelTVDiscrete', '	Channel')		
Command	Value			
ClosedCaption	None			
# ClosedCaption e InterfaceName.Set	xample ('ClosedCaption', None)			
Command	Value			
Freeze	None			
# Freeze example InterfaceName.Set	('Freeze', None)			
Command	Value	Value	Value	
Input	'HDMI 1'	'HDMI 2'	'HDMI 3'	
	'HDMI 4'	'Component'	'Video 1'	
	'Video 2'	'PC'	'TV'	
# Input example InterfaceName.Set	('Input', 'HDMI 1')			
Command	Value	Value	Value	
MenuNavigation	'Up'	'Down'	'Left'	
	'Right'	'Menu'	'Enter'	
	'Exit'			
# MenuNavigation InterfaceName.Set			·	
Command	Value	Value		
Power	'On'	'Off'		
# Power example InterfaceName.Set('Power', 'On')				
Command	Value			
Volume	0 to 100 in steps of 1	[
# Volume example InterfaceName.Set	('Volume', 100)			
Channel Ranges				

¹ Channel Ranges

DTV Air: 100-9999
 DTV Cable 2: 0-9999
 DTV Cable 3: 0-6383
 Cable Major: 1-999

Revision: 8/29/2018

o Cable Minor: 0-999

o TV: 0-135

Revision: 8/29/2018

Status Available

For all commands, call Update to receive the latest status. ConnectionStatus does not support the Update function and is triggered by the device providing a successful response to other Update function calls.

Format with Qualifier:

```
InterfaceName.Update(Command, {'Qualifier Key': 'Qualifier Value'})
Value = InterfaceName.ReadStatus(Command, {'Qualifier Key': 'Qualifier Value'})
InterfaceName.SubscribeStatus(Command, {'Qualifier Key': 'Qualifier Value'}, FeedbackHandler)
FeedbackHandler will be called only when the specified qualifier gets a new status.
```

Format without Qualifier:

InterfaceName.Update(Command)
Value = InterfaceName.ReadStatus(Command)
InterfaceName.SubscribeStatus(Command, None, FeedbackHandler)
FeedbackHandler will be called when any qualifier gets a new status.

Command	Value	Value	Value
AspectRatio	'Side Bar'	'S.Stretch'	'Zoom [AV]'
	'Stretch [AV]'	'Normal [PC]'	'Zoom [PC]'
	'Stretch [PC]'	'Dot by Dot [PC]'	'Full Screen [AV]'
	'Auto'	'Original'	
# AspectRatio examples InterfaceName.Update('AspectRatio') Value = InterfaceName.ReadStatus('AspectRatio') InterfaceName.SubscribeStatus('AspectRatio', None, FeedbackHandler)			
Command	Value	Value	
AudioMute	'On'	'Off'	
<pre>InterfaceName.Update Value = InterfaceNam InterfaceName.Subscr Command ChannelDTVAirStatus</pre>	e.ReadStatus('AudioM	lute') ', None, FeedbackHandler)	
# ChannelDTVAirStatus examples InterfaceName.Update('ChannelDTVAirStatus') Value = InterfaceName.ReadStatus('ChannelDTVAirStatus') InterfaceName.SubscribeStatus('ChannelDTVAirStatus', None, FeedbackHandler)			
Command ChannelDTVCableMajorSt	Qualifier Value 'String'		
atus	58		
# ChannelDTVCableMajorStatus examples InterfaceName.Update('ChannelDTVCableMajorStatus') Value = InterfaceName.ReadStatus('ChannelDTVCableMajorStatus') InterfaceName.SubscribeStatus('ChannelDTVCableMajorStatus', None, FeedbackHandler)			

Revision: 8/29/2018

Command	Qualifier Value		
ChannelDTVCableMinorSt	'String'	'String'	
atus			
InterfaceName.Update(Value = InterfaceName	nelDTVCableMinorStatus examples aceName.Update('ChannelDTVCableMinorStatus') = InterfaceName.ReadStatus('ChannelDTVCableMinorStatus') aceName.SubscribeStatus('ChannelDTVCableMinorStatus', None, FeedbackHandler)		
Command	Qualifier Value		
ChannelDTVCable2Status	'String'		
Value = InterfaceName	'ChannelDTVCable2Status') .ReadStatus('ChannelDTVCab	ole2Status') !Status', None, FeedbackHar	ndler)
Command ChannelDTVCable3Status	Qualifier Value 'String'		
InterfaceName.Update(Value = InterfaceName	# ChannelDTVCable3Status examples InterfaceName.Update('ChannelDTVCable3Status') Value = InterfaceName.ReadStatus('ChannelDTVCable3Status') InterfaceName.SubscribeStatus('ChannelDTVCable3Status', None, FeedbackHandler)		
Command ChannelTVStatus	Qualifier Value 'String'		
ConnectionStatus	Value 'Connected'	Value 'Disconnected'	
<pre>ConnectionStatus # ConnectionStatus ex Value = InterfaceName</pre>	'Connected'	'Disconnected'	
# ConnectionStatus ex Value = InterfaceName InterfaceName.Subscri	'Connected' amples .ReadStatus('ConnectionStatus beStatus('ConnectionStatus Value	'Disconnected' otus') ', None, FeedbackHandler) Value	Value
# ConnectionStatus ex Value = InterfaceName InterfaceName.Subscri	'Connected' amples .ReadStatus('ConnectionStatus beStatus('ConnectionStatus Value 'HDMI 1'	'Disconnected' itus') ', None, FeedbackHandler) Value 'HDMI 2'	'HDMI 3'
# ConnectionStatus ex Value = InterfaceName InterfaceName.Subscri	'Connected' amples .ReadStatus('ConnectionStatus beStatus('ConnectionStatus Value 'HDMI 1' 'HDMI 4'	'Disconnected' itus') '', None, FeedbackHandler) Value 'HDMI 2' 'Component'	
# ConnectionStatus ex Value = InterfaceName InterfaceName.Subscri Command Input # Input examples InterfaceName.Update(Value = InterfaceName	'Connected' amples .ReadStatus('ConnectionStatus beStatus('ConnectionStatus Value 'HDMI 1' 'HDMI 4' 'Video 2' 'Input')	'Disconnected' Itus') Value 'HDMI 2' 'Component' 'PC'	'HDMI 3'
# ConnectionStatus ex Value = InterfaceName InterfaceName.Subscri Command Input # Input examples InterfaceName.Update(Value = InterfaceName	'Connected' amples .ReadStatus('ConnectionStatus beStatus('ConnectionStatus Value 'HDMI 1' 'HDMI 4' 'Video 2' 'Input') .ReadStatus('Input')	'Disconnected' Itus') Value 'HDMI 2' 'Component' 'PC'	'HDMI 3'
# ConnectionStatus ex Value = InterfaceName InterfaceName.Subscri Command Input # Input examples InterfaceName.Update(Value = InterfaceName InterfaceName.Subscri Command Power # Power examples InterfaceName.Update(Value = InterfaceName	'Connected' amples .ReadStatus('ConnectionStatus beStatus('ConnectionStatus Value 'HDMI1' 'HDMI4' 'Video 2' 'Input') .ReadStatus('Input') beStatus('Input', None, Fe Value 'On'	'Disconnected' Intus') Value 'HDMI 2' 'Component' 'PC' RedbackHandler) Value 'Off'	'HDMI 3'

Revision: 8/29/2018

Volume	0 to 100 in steps of 1	
<pre># Volume examples InterfaceName.Update('Volume')</pre>		
Value = InterfaceName.ReadStatus('Volume') InterfaceName.SubscribeStatus('Volume', None, FeedbackHandler)		

Revision: 8/29/2018

Cable and Adapter Requirements


Captive Screw to Female DB9 RS-232 Serial Cable

Notes for the Device


Serial communication

Port Type:RS-232Parity:NoneBaud Rate:9600Stop Bits:OneData Bits:8Flow Control:None

Pin Assignments Diagram



Signal	Main Cable	Pin	Signal
TxD	\longrightarrow	2	RxD
RxD		3	TxD
GND		5	GND



Revision: 8/29/2018

Network communication

When configuring the Ethernet module, be sure device settings match those of the Global Scripter ethernet interface

Port Type: Ethernet

Default Port: 10002

Logon Credentials

Yes

Supported:

Multi-Connection

No

Capabilities:

Port Changeability: Yes

Ethernet Module Configuration Description

Please refer to user manual for settings and changes to the network communication

Notes for the Device

Rev. B

Appendix A. Set Commands

Assest Datis Auto	WIDE10 \x0D
Aspect Ratio Auto	· ·
Aspect Ratio Dot by Dot [PC]	WIDE8 \x0D
Aspect Ratio Full Screen [AV]	WIDE9 \x0D
Aspect Ratio Normal [PC]	WIDE5 \x0D
Aspect Ratio Original	WIDE11 \x0D
Aspect Ratio S.Stretch	WIDE2 \x0D
Aspect Ratio Side Bar	WIDE1 \x0D
Aspect Ratio Stretch [AV]	WIDE4 \x0D
Aspect Ratio Stretch [PC]	WIDE7 \x0D
Aspect Ratio Zoom [AV]	WIDE3 \x0D
Aspect Ratio Zoom [PC]	WIDE6 \x0D
Audio Input None	ACHA0 \x0D
Audio Mute Off	MUTE2 \x0D
Audio Mute On	MUTE1 \x0D
Channel Step Down	RCKY35 \x0D
Channel Step Up	RCKY34 \x0D
Closed Caption None	CLCP0 \x0D
Freeze None	RCKY54 \x0D
Input Component	IAVD5 \x0D
Input HDMI 1	IAVD1 \x0D
Input HDMI 2	IAVD2 \x0D
Input HDMI 3	IAVD3 \x0D
Input HDMI 4	IAVD4 \x0D
Input PC	IAVD8 \x0D
Input TV	ITVD0 \x0D
Input Video 1	IAVD6 \x0D
Input Video 2	IAVD7 \x0D
Menu Navigation Down	RCKY42 \x0D
Menu Navigation Enter	RCKY40 \x0D
Menu Navigation Exit	RCKY46 \x0D
Menu Navigation Left	RCKY43 \x0D
Menu Navigation Menu	RCKY38 \x0D
Menu Navigation Right	RCKY44 \x0D
Menu Navigation Up	RCKY41 \x0D
Power On	POWR1 \x0D
Set Channel DTV Air None	DA2PChannel \x0D

Revision: 8/29/2018

Set Channel DTV Cable Major None	DC2UChannel \x0D
Set Channel DTV Cable Minor None	DC2LChannel \x0D
Set Channel DTV Cable2 None	DC10Channel \x0D
Set Channel DTV Cable3 None	DC11Channel \x0D
Set Channel TV None	DCCHChannel \x0D
Volume 0	VOLM000 \x0D
Volume 100	VOLM100 \x0D

Appendix B. Update Commands

Aspect Ratio	WIDE????\x0D
Audio Mute	MUTE????\x0D
Channel DTV Air Status	DA2P????\x0D
Channel DTV Cable Major Status	DC2U????\x0D
Channel DTV Cable Minor Status	DC2L????\x0D
Channel DTV Cable2 Status	DC10????\x0D
Channel DTV Cable3 Status	DC11????\x0D
Channel TV Status	DCCH????\x0D
Input	IAVD????\x0D
Power	POWR????\x0D
Volume	VOLM????\x0D